Setup your rooms

Array key is used as label in Grafana / tag for measurements

Polling configuration

```
Config file: php/config/poll_config.php
  'influxdb_host' => 'localhost',
  'influxdb_port' => '8086',
  'poll_interval' => 30,
  'poll_sleep_between_requests' => 2,
  'verbose' => FALSE,
  'delaying_start_seconds' => 10,
```

 ${\tt delaying_start_seconds}$ can be helpful to not have supervisor terminate on first startup. use 0 or false to not delay start.

Debugging / Logs

```
docker ps
docker exec -it <container-id> bash
```